

Trazer User Manual



- [Introduction](#)
- [Command-Line Parameters](#)
- [Configuration file](#)
- [Human Readable Output](#)
- [Trazer revision history](#)

Introduction

Trazer is a visualization tool that works in conjunction with the RKH Framework built in trace facility. Trazer gives the possibility to display selectively the recording of all events of your system, state machines, queues, timers etc. Trazer helps you to faster troubleshooting especially on complex problems where a debugger is not sufficient, by providing a simple consolidated, human-readable textual output.

Given the RKH cross platform portability, trace data may come from 8, 16, or 32 bit machines. In order to that Trazer need to be configured to support this diversity of platform and the wide range of RKH framework configurations.

Trazer requires these setups:

- [Command-Line Parameters](#) to configure communication link and general options.
- [Configuration file](#) (trazer.cfg) to setup all target dependencies, such as pointer sizes, signal sizes, etc.

Command-Line Parameters

| Option | Example | Comments |
|--------|---------|-------------------------------------|
| -h | -h | Help. Prints the summary of options |

| | | |
|----|--------------------|--|
| -q | -q | Quiet mode (no stdout output) |
| -v | -v | Visualize Traze version and compatibility with RKH framework |
| -o | -o trazer.txt | Produce output to the specified file |
| -c | -c COM1 115200 8N1 | COM port and baudrate selection. Not compatible with -t, -f |
| -t | -t 6602 | TCP/IP server and port number. Not compatible with -c, -f |
| -f | -f trace.bin | File input selection. Not compatible with -c, -t |

Configuration file

Trazer is designed to work with all possible target CPU, which requires a wide range of configurability. For example, for any given target CPU, Trazer must "know" the size of object pointers, event size, timestamp size and so on. You can provide this information by two ways:

- including "trazer.cfg" configuration file in trazer.exe directory.
- setup the target application to call to RKH_TR_FWK_TCFG and perform the streaming the RKH configuration at startup.

If config file is not found, assuming default settings, any configuration streaming received overwrite settings.

the following table summarizes the "trazer.cfg" content.

| Parameter | Valid Values | Must match RKH config (rkhcfg.h) | Comments |
|-----------------------|--------------|----------------------------------|--|
| TRAZER_SIZEOF_SIG | 1, 2, 4 | #RKH_SIZEOF_EVENT | Event Signal size in bytes. |
| TRAZER_SIZEOF_TSTAMP | 1, 2, 4 | #RKH_TRC_SIZEOF_TSTAMP | Bytes quantity used by the trace record timestamp. |
| TRAZER_SIZEOF_POINTER | 1, 2, 4 | #RKH_TRC_SIZEOF_POINTER | Size in bytes of void pointer. |
| TRAZER_SIZEOF_NTIMER | 1, 2, 4 | #RKH_TIM_SIZEOF_NTIMER | Dynamic range of time delays measured in ticks and expressed in bytes. |
| TRAZER_SIZEOF_NBLOCK | 1, 2, 4 | #RKH_MP_SIZEOF_NBLOCK | Size in bytes of number of memory block size. |
| | | | Maximum number of elements in |

| | | | |
|---------------------|---------|----------------------|--|
| TRAZER_SIZEOF_NELEM | 1, 2, 4 | #RKH_RQ_SIZEOF_NELEM | bytes that any queue can contain. |
| TRAZER_SIZEOF_ESIZE | 1, 2, 4 | #RKH_SIZEOF_ESIZE | Data type of event size, in bytes. |
| TRAZER_EN_NSEQ | 0, 1 | #RKH_TRC_EN_NSEQ | Enable/Disable Number of Sequence use in trace stream. |
| TRAZER_EN_CHK | 0, 1 | #RKH_TRC_EN_CHK | Enable/Disable Checksum use in trace stream. |
| TRAZER_EN_TSTAMP | 0, 1 | #RKH_TRC_EN_TSTAMP | Enable/Disable Time stamp use in trace stream. |

Your must ensure that Trazer configuration, match exactly with the target system under test, otherwise will be unable to parse the trace stream, and these errors would be shown:

***** Stream Checksum Error

***** May be have lost trace info, sequence are not correlatives

Two particular trace event can be used to better trace visualization.

RKH_TRCE_OBJ: Allows to asociate any aplication object allocated in a memory address to a user defined name.

RKH_TRCE_SIG: Allows to asociate a any framework signal that generate trace events to a user defined name.

RKH user must generate this particulars trace events as described in RKHTRACE and Trazer will take care of reemplacing the numeric values by the user definition.

Human Readable Output

Trazer is a console program that converts the trace stream data in a human-readable format. Following is shown how its output looks like.

Trazer start showing version and compatibility with RKH framework, below are displayed the current Trazer configuration. For this example the trace.bin is used as trace data source.

Each identified trace show:

- Time stamp, in cpu ticks.
- Sequence Number, correlative number that identify trace event.
- System service group name.
- Trace Event Alias, user defined alias from trazer.evt
- Data asociated with the event.
- Comment.

Sequences 4, 5 and 6 are examples of RKH_TRCE_OBJ and RKH_TRCE_SIG events. After, sequences 16, 17, 32 and 33, show how Trazer identify object address and signal number replacing them by its

symbolic representation. In case that no symbolic representation has been defined for a particular object, (null) will be shown, and in same manner the numeric value for signals.

TRAZER Visualization Tool V2.0 compatible with RKH V2.3

Date = Jan 31 2013 13:46:48

Trace Setup

```
Trace events quantity = 45
TRAZER_SIZEOF_SIG      = 1
TRAZER_SIZEOF_TSTAMP   = 4
TRAZER_SIZEOF_POINTER  = 4
TRAZER_SIZEOF_NTIMER   = 2
TRAZER_SIZEOF_NBLOCK   = 1
TRAZER_SIZEOF_NELEM    = 1
TRAZER_SIZEOF_ESIZE    = 2
TRAZER_EN_NSEQ         = 1
TRAZER_EN_CHK          = 1
TRAZER_EN_TSTAMP       = 1
RKH_TRC_ALL            = 1
RKH_TRC_EN_MP          = 0
RKH_TRC_EN_RQ          = 0
RKH_TRC_EN_SMA         = 0
RKH_TRC_EN_TIM         = 0
RKH_TRC_EN_SM          = 0
RKH_TRC_EN_RKH        = 0
```

----- Parsing trace stream from file trace.bin -----

```
      84 [  0] MP   | INIT           : mp=(null), nblock=16 : Memory
Pool Init
      84 [  1] RKH | EPOOL_REG       : epix =1, ssize=64, esize=4
      84 [  2] MP   | INIT           : mp=(null), nblock=4  : Memory P
ool Init
      84 [  3] RKH | EPOOL_REG       : epix =2, ssize=32, esize=8
      84 [  4] RKH | SYM_OBJ         : obj=0x01091780, sym=&rkheplist[
0]
      84 [  5] RKH | SYM_OBJ         : obj=0x01091794, sym=&rkheplist[
1]
      84 [  6] RKH | SYM_SIG         : sig=1, sym=ONE
      84 [  7] RQ   | INIT           : rq=(null), sma=(null), nelem=4
      84 [  8] SMA  | REGISTER        : sma=(null), prio=0
      84 [  9] SM   | INIT           : sma=(null), istate=(null)
      84 [ 10] TIM  | INIT           : timer=(null), sig=(null)
      84 [ 11] SM   | ENTRY_STATE    : sma=(null), state=(null)
      84 [ 12] SM   | ENTRY_STATE    : sma=(null), state=(null)
      84 [ 13] SM   | ENTRY_STATE    : sma=(null), state=(null)
      84 [ 14] SMA  | ACTIVATE       : sma=(null)
      86 [ 15] RKH | ENTER           :
```

```

1509 [ 16] MP | GET : mp=&rkheplist[1], nfree=3 : Memory Pool Get
1509 [ 17] RKH | ALLOC_EVENT : esize=6, sig=ONE
1509 [ 18] RQ | POST_FIFO : rq=(null), nused=1
1509 [ 19] SMA | POST_FIFO : sma=(null), sig=ONE
1509 [ 20] RQ | GET_LAST : rq=(null)
1509 [ 21] SMA | GET_EVENT : sma=(null), sig=ONE
1509 [ 22] SM | DISPATCH : sma=(null), sig=ONE
1509 [ 23] SM | TRANSITION : sma=(null), sstate=(null), tstate=(null)
1509 [ 24] SM | COMP_STATE : sma=(null), state=(null)
1509 [ 25] SM | NUM_EN_EX : sma=(null), nentry=1, nexit=1
1509 [ 26] SM | EXIT_STATE : sma=(null), state=(null)
1509 [ 27] SM | NUM_TRN_ACT : sma=(null), ntrnaction=1
1509 [ 28] SM | ENTRY_STATE : sma=(null), state=(null)
1509 [ 29] SM | CURRENT_STATE : sma=(null), state=(null)
1509 [ 30] SM | DISPATCH_RCODE : sma=(null), retcode=RKH_OK
1509 [ 31] RKH | GC_RECYCLE : sig=ONE
1509 [ 32] MP | PUT : mp=&rkheplist[1], nfree=4
1905 [ 33] MP | GET : mp=&rkheplist[1], nfree=3 : Memory Pool Get
1905 [ 34] RKH | ALLOC_EVENT : esize=6, sig=(null)
1905 [ 35] RQ | POST_FIFO : rq=(null), nused=1

```

Licensing Trazer

Trazer application is licensed the same way as all other components of the RKH framework. See section licensing.

Copyright © 2010-2012 Vortex Technologies. All Rights Reserved.

e-mail: dariosb@gmail.com